

NAME atof -- ascii to floating

SYNOPSIS jsr r5,atof; subr

DESCRIPTION atof will convert an ascii stream to a floating number returned in r0. The subroutine subr is called on r5 for each character of the ascii stream. subr should return the character in r0. The first character not used in the conversion is left in r0. The floating point simulation should be active in either floating or double mode, but in single precision integer mode.

FILES kept in /etc/liba.a

SEE ALSO fptrap

DIAGNOSTICS --

BUGS The subroutine subr should not disturb any registers.

OWNER ken

11/3/71

ATOI (III)

NAME atoi -- ascii to integer

SYNOPSIS jsr r5,atoi; subr

DESCRIPTION atoi will convert an ascii stream to a binary
 number returned in mq. The subroutine subr is
 called on r5 for each character of the ascii
 stream. subr should return the character in r0.
 The first character not used in the conversion is
 left in r0.

FILES kept in /etc/liba.a

SEE ALSO --

DIAGNOSTICS --

BUGS The subroutine subr should not disturb any regis-
 ters.

OWNER ken

11/3/71

CTIME (III)

NAME ctime -- convert date and time to ASCII

SYNOPSIS (move time to AC-MQ)
 mov \$buffer,r0
 jsr pc,ctime

DESCRIPTION The buffer is 15 characters long. The time has
 the format

 Oct 9 17:32:24

 The input time is in the AC and MQ registers in
 the form returned by sys time.

FILES kept in /etc/liba.a

SEE ALSO ptime, to print time; sys time

DIAGNOSTICS --

BUGS The time is not taken modulo 1 year. (Jan 1
 comes out Dec 32.) Also, the clock period is only
 a couple of years.

OWNER dmr

11/3/71

EXP (III)

NAME exp -- exponential function

SYNOPSIS jsr r5,exp

DESCRIPTION The exponential of fr0 is returned in fr0. The floating point simulation should be active in either floating or double mode, but in single precision integer mode.

FILES kept in /etc/liba.a

SEE ALSO fptrap

DIAGNOSTICS --

BUGS Large arguments will cause an overflow fault from the floating point simulator.

OWNER ken

11/3/71

FPTRAP (III)

NAME fptrap -- floating point simulator

SYNOPSIS sys 33.; fptrap

DESCRIPTION fptrap is a program designed to pick up illegal instruction in order to simulate a sub-set of the 11/45 floating point hardware.

FILES kept in /etc/liba.a

SEE ALSO as, PDP-11/45 manual

DIAGNOSTICS none, hardware gives no diagnostics.

BUGS The simulation, if unsuccessful for any reason gives an IOT fault from inside the simulator. This should be handled better.

OWNER ken, dmr

11/3/71

FTOA (III)

NAME ftoa -- floating to ascii conversion

SYNOPSIS jsr r5,ftoa; subr

DESCRIPTION ftoa will convert the floating point number in
r0 into ascii in the form [-]d.dddde[-]dd*.
The floating point simulator should be active in
either floating or double mode, but in single
integer mode. For each character generated by
ftoa, the subroutine subr is called on register
r5 with the character in r0.

FILES kept in /etc/liba.a

SEE ALSO fptrap

DIAGNOSTICS --

BUGS The subroutine subr should not disturb any regis-
ters.

OWNER ken

NAME getw, getc, fopen -- buffered input

```
SYNOPSIS        mov        $filename,r0
                  jsr        r5,fopen; iobuf

                  jsr        r5,getc; iobuf
                  (character in r0)

                  jsr        r5,getw; iobuf
                  (word in r0)
```

DESCRIPTION These routines are used to provide a buffered input facility. iobuf is the address of a 134(10) byte buffer area whose contents are maintained by these routines. Its format is:

```
ioptr:    .=.+2                / file descriptor
          .=.+2                / characters left in buffer
          .=.+2                / ptr to next character
          .=.+128.             / the buffer
```

fopen should be called initially to open the file. On return, the error bit (c-bit) is set if the open failed. If fopen is never called, get will read from the standard input file.

getc returns the next byte from the file in r0. The error bit is set on end of file or a read error.

getw returns the next word in r0. getc and getw may be used alternately; there are no odd/even problems.

iobuf must be provided by the user; it must be on a word boundary.

FILES kept in /etc/liba.a

SEE ALSO sys open, sys read; putc, putw, fcreat

DIAGNOSTICS c-bit set on EOF or error

BUGS for greater speed, the buffer should be 512 bytes long. Unfortunately, this will cause several existing programs to stop working.

OWNER dmr

11/3/71

ITOA (III)

NAME itoa -- integer to ascii conversion

SYNOPSIS jsr r5, itoa; subr

DESCRIPTION itoa will convert the number in r0 into ascii
decimal possibly preceded by a - sign. For each
character generated by itoa, the subroutine subr
is called on register r5 with the character in
r0.

FILES kept in /etc/liba.a

SEE ALSO --

DIAGNOSTICS --

BUGS The subroutine subr should not disturb any regis-
ters.

OWNER ken

11/3/71

LOG (III)

NAME log -- logarithm base e

SYNOPSIS jsr r5,log

DESCRIPTION The logarithm base e of fr0 is returned in fr0. The floating point simulation should be active in either floating or double mode, but in single precision integer mode.

FILES kept in /etc/liba.a

SEE ALSO fptrap

DIAGNOSTICS The error bit (c-bit) is set if the input argument is less than or equal to zero.

BUGS --

OWNER ken

11/3/71

MESG (III)

NAME mesg -- write message on typewriter

SYNOPSIS jsr r5,mesg; <Now is the time\0>; .even

DESCRIPTION mesg writes the string immediately following its
call onto the standard output file. The string
is terminated by a 0 byte.

FILES kept in /etc/liba.a, standard output file

SEE ALSO --

DIAGNOSTICS --

BUGS --

OWNER ken, dmr

11/3/71

PTIME (III)

NAME ptime -- print date and time

SYNOPSIS (move time to ac-mq)
mov file,r0
jsr pc,ptime

DESCRIPTION ptime prints the date and time in the form

Oct 9 17:20:33

on the file whose file descriptor is in r0. The string is 15 characters long. The time to be printed is placed in the AC and MQ registers in the form returned by sys time.

FILES kept in /etc/liba.a

SEE ALSO sys time, ctime (used to do the conversion)

DIAGNOSTICS --

BUGS see ctime

OWNER dmr, ken

NAME putc, putw, fcreat, flush -- buffered output

SYNOPSIS mov \$filename,r0
 jsr r5,fcreat; iobuf

 (get byte in r0)
 jsr r5,putc; iobuf

 (get word in r0)
 jsr r5,putw; iobuf

 jsr r5,flush; iobuf

DESCRIPTION fcreat creates the given file (mode 17) and sets up the buffer iobuf (size 134(10) bytes); putc and putw write a byte or word respectively onto the file; flush forces the contents of the buffer to be written, but does not close the file. The format of the buffer is:

```
iobuf:  .=.+2               / file descriptor
         .=.+2               / characters unused in buffer
         .=.+2               / ptr to next free character
         .=.+128.            / buffer
```

fcreat sets the error bit (c-bit) if the file creation failed; none of the other routines return error information.

Before terminating, a program should call flush to force out the last of the output.

The user must supply iobuf, which should begin on a word boundary.

FILES kept in /etc/liba.a

SEE ALSO sys creat; sys write; getc, getw, fopen

DIAGNOSTICS error bit possible on fcreat call

BUGS buffers should be changed to 512 bytes.

OWNER dmr

11/3/71

SIN, COS (III)

NAME sin, cos -- sine cosine

SYNOPSIS jsr r5,sin (cos)

DESCRIPTION The sine (cosine) of fr0 (radians) is returned in fr0. The floating point simulation should be active in either floating or double mode, but in single precision integer mode. All floating registers are used.

FILES kept in /etc/liba.a

SEE ALSO fptrap

DIAGNOSTICS --

BUGS Size of the argument should be checked to make sure the result is meaningful.

OWNER ken, dmr

NAME switch -- switch on value

SYNOPSIS (switch value in r0)
 jsr r5,switch; swtab
 (not-found return)
 ...
 swtab: val1; lab1;
 ...
 valn; labn
 ..; 0

DESCRIPTION switch compares the value of r0 against each of
 the val_i; if a match is found, control is
 transferred to the corresponding lab_i (after pop-
 ping the stack once). If no match has been found
 by the time a null lab_i occurs, switch returns.

FILES kept in /etc/liba.a

SEE ALSO --

DIAGNOSTICS --

BUGS --

OWNER ken, dmr